


# VIRTUAL NETWORKING WITH "ORACLE VM VIRTUALBOX" FROM A "LINUX" PERSPECTIVE



## Summary:

"Oracle VM VirtualBox" provides five virtual networking configurations for the virtual machines of a "Linux" host computer:


a "[Shared Folders](#)" gateway/router



a "[Network Address Translation](#)" ("NAT") router  
(with no internal LAN switching)




a "[Bridged](#)" bridge (with no internal LAN switching)



a "[Host-Only](#)" router  
with internal LAN switching

and


an "[Internal Network](#)" LAN switch with optional DHCP services



# VIRTUAL NETWORK ADAPTERS FOR EACH VIRTUAL MACHINE IN “ORACLE VM VIRTUALBOX”


You can provide up to 4 network adapters for each virtual machine:

Use your right mouse button to click on the desired virtual machine:




Use the left mouse button to click on “Settings” on the popup context menu.

A “..Settings” box will be displayed:




Click on “Network”:



Each of the 4 tabs represents a virtual network adapter that you can activate and configure.

If you click on the drop-down list button to the right of the "Attached to:" field, you will see a list of the virtual networks that "Oracle VM VirtualBox" provides to a virtual machine:



Please note that "NAT" is the virtual "[Network Address Translation](#)" ("NAT") router,

"Bridged Adapter" is the virtual "[Bridged](#)" bridge,

"Host-only Adapter" is the virtual "[Host-Only](#)" router,

and

"Internal Network" is the virtual "[Internal Network](#)" LAN switch.

The operating system of the virtual machine treats all of the virtual network adapters as if they were a real items of hardware:



# VIRTUAL NETWORK ADAPTERS FOR THE HOST COMPUTER IN “ORACLE VM VIRTUALBOX”

In the virtual “Shared Folders” gateway/router, no virtual network adapter is used.

In the virtual “Network Address Translation” (“NAT”), “Bridged” bridge, or “Internet Networking” LAN switch networks, the virtual network adapter in the host computer runs in “stealth mode” and you cannot access or configure it.

In the virtual “Host-Only” router network configuration, the virtual network adapter in the host is a virtual wired Ethernet adapter that is called “`vboxnet0`”

To view and/or configure “`vboxnet0`”:

Open a terminal window.

Type in

```
ifconfig
```

Then press the "Enter" key of your keyboard.

vboxnet0 will probably be the bottom-most network adapter that is displayed:

```
testuser@testuser-VGC-RA820G-UC: ~
File Edit View Search Terminal Help
RX packets:39 errors:0 dropped:0 overruns:0 frame:0
TX packets:39 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:4134 (4.1 KB) TX bytes:4134 (4.1 KB)

vboxnet0 Link encap:Ethernet HWaddr 0a:00:27:00:00:00
inet addr:192.168.56.1 Bcast:192.168.56.255 Mask:255.255.255.0
inet6 addr: fe80::800:27ff:fe00:0/64 Scope:Link
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
RX packets:0 errors:0 dropped:0 overruns:0 frame:0
TX packets:105 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:1000
RX bytes:0 (0.0 B) TX bytes:18060 (18.0 KB)

vmnet1 Link encap:Ethernet HWaddr 00:50:56:c0:00:01
inet addr:172.16.106.1 Bcast:172.16.106.255 Mask:255.255.255.0
inet6 addr: fe80::250:56ff:fec0:1/64 Scope:Link
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
RX packets:0 errors:0 dropped:0 overruns:0 frame:0
TX packets:86 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:1000
RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)

vmnet8 Link encap:Ethernet HWaddr 00:50:56:c0:00:08
inet addr:172.16.211.1 Bcast:172.16.211.255 Mask:255.255.255.0
inet6 addr: fe80::250:56ff:fec0:8/64 Scope:Link
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
RX packets:0 errors:0 dropped:0 overruns:0 frame:0
TX packets:87 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:1000
RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)

testuser@testuser-VGC-RA820G-UC:~$ ifconfig vboxnet0
vboxnet0 Link encap:Ethernet HWaddr 0a:00:27:00:00:00
inet addr:192.168.56.1 Bcast:192.168.56.255 Mask:255.255.255.0
inet6 addr: fe80::800:27ff:fe00:0/64 Scope:Link
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
RX packets:0 errors:0 dropped:0 overruns:0 frame:0
TX packets:105 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:1000
RX bytes:0 (0.0 B) TX bytes:18060 (18.0 KB)

testuser@testuser-VGC-RA820G-UC:~$
```

If you see that “vboxnet0” has an IP address, it means than there is at least one VirtualBox virtual machine that is running and connected to the virtual “Host-Only” router.


In Ubuntu, you can see “vboxnet0” in one other way:

From inside the Ubuntu virtual machine:


Click on “System”.

Click on “Administration”.

Click on “Network Tools”:



Click on the drop down button for “Network Device”.  
Then click on “Unknown Interface (vboxnet0)” in the drop-down list:



The specifications for the virtual “vboxnet0” Ethernet adapter will be displayed:

The screenshot shows a window titled "Devices - Network Tools" with a menu bar containing "Tool", "Edit", and "Help". Below the menu bar are several tabs: "Devices", "Ping", "Netstat", "Traceroute", "Port Scan", "Lookup", "Finger", and "Whois". The "Devices" tab is active, showing a "Network device:" dropdown menu with "Unknown Interface (vboxnet0)" selected and a "Configure" button to its right. Below this is the "IP Information" section, which contains a table with the following data:

Protocol	IP Address	Netmask / Prefix	Broadcast	Scope
IPv6	fe80::800:27ff:fe00:0	64		Link
IPv4	192.168.56.1	255.255.255.0		

Below the IP information table are two columns of data: "Interface Information" and "Interface Statistics".

**Interface Information**

- Hardware address: 0a:00:27:00:00:00
- Multicast: Enabled
- MTU: 1500
- Link speed: not available
- State: Active

**Interface Statistics**

- Transmitted bytes: 25.0 KiB
- Transmitted packets: 143
- Transmission errors: 0
- Received bytes: 0.0 B
- Received packets: 0
- Reception errors: 0
- Collisions: 0

At the bottom of the window, there is a status bar showing "Idle".

## "Shared Folders" GATEWAY/ROUTER

with designated target folder located on the host

with no accessible or visible network interfaces in the host or the virtual machine  
with no upstream routing to the Internet.

Oracle's "Guest Additions" software must be installed into each virtual machine.

"Guest Additions" software is provided to you as an \*.iso CD image file called  
VBoxGuestAdditions.iso

Multiple virtual machines can access the same target folder on the host.

"Shared Folders" must be configured for each virtual machine.


"Windows" virtual machine sees a "Shared Folder" inside the "VBOXSVR" virtual server.

"Linux" virtual machine sees a "Shared Folder" mounted in /media but no access is  
permitted.

The "Shared Folders" gateway/router does not work for Macintosh virtual machines at the  
present time.



No indication in host file system that a folder is being shared.

Host computer



"Shared" Folder(s)  
= host folder access  
from the virtual machine

Virtual Machine



"Shared Folders"  
Gateway/Router

"Windows" virtual machine  
sees a virtual server  
called "VBOXSVR"

Virtual network adapter is not used.

File system of virtual machine  
does not indicate that the "Shared Folder"  
is being shared.

Host has no access to the file system of  
the virtual machine

This is not NFS or FTP.

## **ADDITIONAL INFORMATION ABOUT THE VIRTUAL "SHARED FOLDERS" GATEWAY/ROUTER:**

On a Linux host, you can find "VBoxGuestAdditions.iso" file in the "additions" folder under where you installed VirtualBox (normally /opt/VirtualBox/).

Oracle's instructions for setting up "Shared Folders" for a "Windows" or "Linux" virtual machine can be found at

<http://www.virtualbox.org/manual/ch04.html#sharedfolders>

For additional instructions for setting up "Shared Folders for a "Ubuntu" virtual machine, see


<https://help.ubuntu.com/community/VirtualBox/SharedFolders>

and


<http://www.howtogeek.com/75705/access-shared-folders-in-a-virtualbox-ubuntu-11.04-virtual-machine/>

"Network Address Translation" ("NAT") router  
with NAT service, DHCP server, and upstream routing to the Internet,


Host computer



Virtual Machine



Internet access  
from the virtual machine



"NAT" router  
with NAT service  
with DHCP service  
with upstream routing  
to the Internet  
with LAN switching  
between the host  
and virtual machines  
(with no LAN switching  
between the  
virtual machines)

From inside a Linux virtual  
machine:  
to access folders on the  
host that are shared  
by means of Samba (SMb)  
or "Network File System" (NFS)  
please see  
"Using IP Addresses to  
Access Shared Files and  
Folders" in a Virtual Machine"  
(at the end of this document).

## "Bridged" bridge

with mandatory "TEE" connection to either an upstream, real network adapter (or to an operating system-provided virtual bridge on the host such as the "Windows Network Bridge")

with no internal LAN switching


(with LAN switching between virtual machines performed by the real physical network)

(with LAN switching between the host and virtual machines performed by the real physical network)



(with NAT server and DHCP server provided by the real physical network)

With this virtual network option, the virtual machine(s) participate on the real physical network as "peers" with the host.

Host computer



Virtual Machine



Internet access

from virtual machine

Optional host folder access

from virtual machine

by means of

Windows "File Sharing"

or "Homegroups"

"Bridged" bridge

provides "TEE"

to a real physical

physical network

adapter but does not

switch between

virtual machines

From inside a Linux virtual machine, to access folders on the host or on other virtual machines that are shared by means of Samba (SMB) or NFS please see the section called "Using IP Addresses to Access Folders That are Shared by SAMBA (SMB) or Network File System"(NFS)


(at the end of this document).

In the "Bridged" bridge virtual network, the real physical network provides DHCP services, upstream routing to the Internet, NAT services, LAN switching between the host and virtual machines, and LAN switching between virtual machines.


### "Host-Only" router

with mandatory LAN switching between the host and the virtual machine,  
with LAN switching or routing between virtual machines,  
with an optional DHCP server, no NAT server, and no upstream routing to the Internet


Host computer



Virtual Machine



No Internet Access  
from virtual machine  
Optional host folder access  
from virtual machine  
by means of  
Windows "File Sharing"  
or "Homegroups"



"Host-only" router  
with mandatory LAN switching  
between host and virtual machines  
with LAN switching or routing between  
virtual machines.



Local Area Connection  
Network, Shared  
Intel(R) PRO/1000 MT Desktop Adap...



VirtualBox Host-Only Network  
Unidentified network  
VirtualBox Host-Only Ethernet Adapter

Host has a "Virtual Host-Only Ethernet Adapter"  
which connects the file system of the host  
to the "Host-only" router

The "Host-only" router acts as a firewall to prevent communications between the Internet  
and all virtual machines.

This is the hardest configuration to set up:

It often takes a multiple reboots and long waits before the host can see shared files on the virtual machines and vice versa.

Sometimes it is necessary to attach more than one virtual machine to the "Host-only" router before file sharing starts up between virtual machines and between virtual machines and the host.

### "Internal Network" switch ("intnet")


with LAN switching between virtual machines

with no LAN switching or routing between virtual machines and the host



with an optional DHCP server (a router function)

with no NAT server, and no upstream routing to the Internet

Host computer



Virtual Machine



Local Area Connection  
Network, Shared  
Intel(R) PRO/1000 MT Desktop Adap...

No host folder access  
from virtual machine  
No internet access  
from virtual machine

"intnet"  
switch  
with  
LAN switching  
between  
virtual  
machines

Optional  
DHCP  
server

From inside a Linux virtual machine, to access folders on other virtual machines that are shared by means of Samba (SMB) or Network File System (NFS) please see the section called

"Using IP Addresses to Access Folders That are Shared by SAMBA (SMB) or "Network File System"(NFS))  
at the end of this document).

# USING IP ADDRESSES TO ACCESS FOLDERS THAT ARE SHARED BY SAMBA(SMB) OR “NETWORK FILE SYSTEM”(NFS)

Computers that are attached to local area networks (LANs) are often real slow to discover the files and printers that are shared from other LAN-attached computers so you sometimes have to help them connect to other computers for file and folder sharing.

In the following two situations, you sometimes need to proactively force a connection between two LAN-attached computers:

## SITUATION 1:

When you are inside a “VirtualBox” virtual machine and you need to access a files that is shared from the host computer by means of SAMBA (SMB) or Network File System (NFS)

or

## SITUATION 2:

When you are working in the host comptuer and you need to acces a file that is shared from within a “VirtualBox” virtual machine by means of SAMBA (SMB) or Network File System (NFS).

## STEP-BY-STEP PROCEDURE:

Step 1:

Go to the computer where the files or folders are being shared from.

Step 2:

Open a terminal window:

Step 3:

If the computer is a “Windows” computer, type in

`ipconfig /all`

and press the enter key.

If the computer is a Linux computer, type in

`ifconfig`

and press the enter key:

#### Step 4:

Locate the IP address of the real network adapter and write it down.

In our example, the IP address is

127.0.0.1

```
testuser@testuser-VGC-RA820G-UC: ~
File Edit View Search Terminal Help
collisions:0 txqueuelen:1000
RX bytes:1506814 (1.5 MB) TX bytes:238224 (238.2 KB)

lo    Link encap:Local Loopback
      inet addr:127.0.0.1  Mask:255.0.0.0
      inet6 addr: ::1/128 Scope:Host
      UP LOOPBACK RUNNING MTU:16436 Metric:1
      RX packets:466 errors:0 dropped:0 overruns:0 frame:0
      TX packets:466 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:69688 (69.6 KB) TX bytes:69688 (69.6 KB)

vboxnet0  Link encap:Ethernet  HWaddr 0a:00:27:00:00:00
      inet addr:192.168.56.1 Bcast:192.168.56.255 Mask:255.255.255
      inet6 addr: fe80::800:27ff:fe00:0/64 Scope:Link
      UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:278 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:1000
      RX bytes:0 (0.0 B) TX bytes:54138 (54.1 KB)

vmnet1    Link encap:Ethernet  HWaddr 00:50:56:c0:00:01
      inet addr:172.16.106.1 Bcast:172.16.106.255 Mask:255.255.255
      inet6 addr: fe80::250:56ff:fec0:1/64 Scope:Link
      UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:169 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:1000
      RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)

vmnet8    Link encap:Ethernet  HWaddr 00:50:56:c0:00:08
      inet addr:172.16.211.1 Bcast:172.16.211.255 Mask:255.255.255
      inet6 addr: fe80::250:56ff:fec0:8/64 Scope:Link
      UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:165 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:1000
      RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)
```

## Step 5:

Go to the virtual or real computer from which you wish to access the files on the source computer and click on open a “Nautilus” file management window if this computer is running Linux.

If the virtual or real computer from which you wish to access the files on the source computer is a Ubuntu Linux computer, click on “Places” and then click on “Computer”:




\*

Step 6:

If you now have a “Windows Explorer”, “My Computer” or “Computer” windows, go to it's address box.

If you now have a “Nautilus” window, click on “Go”. Then click on “Location”:




### Step 7:

In the address box, type in `smb://<ip address of destination>` and then press the enter key of the keyboard. In our example, we type in


smb://10.0.0.34

and then we pressed the enter key:




Step 8:

All of the shared folders on the target will be displayed:



Note that all remote files that are shared via "Samba"("SMB" are called "Windows shares" by the "Ubuntu" operating system.

In this example, a shared folder and a shared printer are displayed. If you double-click on the shared folder, you will see it's contents:



Please do not confuse these shared folders with those shared by means of the “Shared Folders” gateway/router. These shared folders are shared by means of standard sharing mechanisms such as “Samba” (SMB) and “Network File System” (NFS) and these standard file sharing mechanisms utilize the virtual Ethernet adapter(s) that is provided to the virtual machine by “VirtualBox”. The “Shared Folders” gateway/router provides for one-way file sharing that is proprietary to the “VirtualBox” software application—it can only share folders that are located on the host computer.

## References:

<http://www.virtualbox.org/manual/ch06.html>

<http://www.dedoimedo.com/computers/virtualbox-network-sharing.html>

<http://www.virtualbox.org/manual/UserManual.html>

[http://ninjazeera.com/virtualbox\\_network\\_scenarios](http://ninjazeera.com/virtualbox_network_scenarios)